

Virtual Art Therapy: Research and Practice

VK_LBUTTON 0x01 Left mouse button

VK_RBUTTON 0x02 Right mouse button

VK_CANCEL 0x03 Control-break processing

VK_MBUTTON 0x04 Middle mouse button (three-button mouse)

VK_XBUTTON1 0x05 X1 mouse button

VK_XBUTTON2 0x06 X2 mouse button

- 0x07 Undefined

VK_BACK 0x08 BACKSPACE key

VK_TAB 0x09 TAB key

- 0x0A-0B Reserved

VK_CLEAR 0x0C CLEAR key

VK_RETURN 0x0D ENTER key

- 0x0E-0F Undefined

VK_SHIFT 0x10 SHIFT key

VK_CONTROL 0x11 CTRL key

VK_MENU 0x12 ALT key

VK_PAUSE 0x13 PAUSE key

VK_CAPITAL 0x14 CAPS LOCK key

VK_KANA 0x15 IME Kana mode

VK_HANGUEL 0x15 IME Hanguel mode (maintained for compatibility; use VK_HANGUL)

VK_HANGUL 0x15 IME Hangul mode

VK_IME_ON 0x16 IME On

VK_JUNJA 0x17 IME Junja mode

VK_FINAL 0x18 IME final mode

VK_HANJA 0x19 IME Hanja mode

P

VK_KANJI 0x19 IME Kanji mode

VK_IME_OFF 0x1A IME Off

VK_ESCAPE 0x1B ESC key

VK_CONVERT 0x1C IME convert

VK_NONCONVERT 0x1D IME nonconvert

VK_ACCEPT 0x1E IME accept

VK_MODECHANGE 0x1F IME mode change request

VK_SPACE 0x20 SPACEBAR

VK_PRIOR 0x21 PAGE UP key

VK_NEXT 0x22 PAGE DOWN key

VK_END 0x23 END key

VK_HOME 0x24 HOME key

VK_LEFT 0x25 LEFT ARROW key

VK_UP 0x26 UP ARROW key

VK_RIGHT 0x27 RIGHT ARROW key

VK_DOWN 0x28 DOWN ARROW key

VK_SELECT 0x29 SELECT key

VK_PRINT 0x2A PRINT key

VK_EXECUTE 0x2B EXECUTE key

VK_SNAPSHOT 0x2C PRINT SCREEN key

VK_INSERT 0x2D INS key

VK_DELETE 0x2E DEL key

VK_HELP 0x2F HELP key

0x30 0 key

0x31 1 key

0x32 2 key

0x33 3 key

0x34 4 key

0x35 5 key

0x36 6 key

0x37 7 key

0x38 8 key

0x39 9 key

- 0x3A-40 Undefined

0x41 A key

0x42 B key

0x43 C key

0x44 D key

0x45 E key

0x46 F key

0x47 G key

0x48 H key

0x49 I key

0x4A J key

0x4B K key

0x4C L key

0x4D M key

0x4E N key

0x4F O key

0x50 P key

0x51 Q key

0x52 R key

0x53 S key

0x54 T key

0x55 U key

0x56 V key

0x57 W key

0x58 X key

0x59 Y key

0x5A Z key

VK_LWIN 0x5B Left Windows key (Natural keyboard)

VK_RWIN 0x5C Right Windows key (Natural keyboard)

VK_APPS 0x5D Applications key (Natural keyboard)

- 0x5E Reserved

VK_SLEEP 0x5F Computer Sleep key
VK_NUMPAD0 0x60 Numeric keypad 0 key
VK_NUMPAD1 0x61 Numeric keypad 1 key
VK_NUMPAD2 0x62 Numeric keypad 2 key
VK_NUMPAD3 0x63 Numeric keypad 3 key
VK_NUMPAD4 0x64 Numeric keypad 4 key
VK_NUMPAD5 0x65 Numeric keypad 5 key
VK_NUMPAD6 0x66 Numeric keypad 6 key
VK_NUMPAD7 0x67 Numeric keypad 7 key
VK_NUMPAD8 0x68 Numeric keypad 8 key
VK_NUMPAD9 0x69 Numeric keypad 9 key
VK_MULTIPLY 0x6A Multiply key
VK_ADD 0x6B Add key
VK_SEPARATOR 0x6C Separator key
VK_SUBTRACT 0x6D Subtract key
VK_DECIMAL 0x6E Decimal key

VK_DIVIDE 0x6F Divide key

VK_F1 0x70 F1 key

VK_F2 0x71 F2 key

VK_F3 0x72 F3 key

VK_F4 0x73 F4 key

VK_F5 0x74 F5 key

VK_F6 0x75 F6 key

VK_F7 0x76 F7 key

VK_F8 0x77 F8 key

VK_F9 0x78 F9 key

VK_F10 0x79 F10 key

VK_F11 0x7A F11 key

VK_F12 0x7B F12 key

VK_F13 0x7C F13 key

VK_F14 0x7D F14 key

VK_F15 0x7E F15 key

VK_F16 0x7F F16 key

VK_F17 0x80 F17 key

VK_F18 0x81 F18 key

VK_F19 0x82 F19 key

VK_F20 0x83 F20 key

VK_F21 0x84 F21 key

VK_F22 0x85 F22 key

VK_F23 0x86 F23 key

VK_F24 0x87 F24 key

- 0x88-8F Unassigned

VK_NUMLOCK 0x90 NUM LOCK key

VK_SCROLL 0x91 SCROLL LOCK key

0x92-96 OEM specific

- 0x97-9F Unassigned

VK_LSHIFT 0xA0 Left SHIFT key

VK_RSHIFT 0xA1 Right SHIFT key

VK_LCONTROL 0xA2 Left CONTROL key

VK_RCONTROL 0xA3 Right CONTROL key

VK_LMENU 0xA4 Left ALT key

VK_RMENU 0xA5 Right ALT key

VK_BROWSER_BACK 0xA6 Browser Back key

VK_BROWSER_FORWARD 0xA7 Browser Forward key

VK_BROWSER_REFRESH 0xA8 Browser Refresh key

VK_BROWSER_STOP 0xA9 Browser Stop key

VK_BROWSER_SEARCH 0xAA Browser Search key

VK_BROWSER_FAVORITES 0xAB Browser Favorites key

VK_BROWSER_HOME 0xAC Browser Start and Home key

VK_VOLUME_MUTE 0xAD Volume Mute key

VK_VOLUME_DOWN 0xAE Volume Down key

VK_VOLUME_UP 0xAF Volume Up key

VK_MEDIA_NEXT_TRACK 0xB0 Next Track key

VK_MEDIA_PREV_TRACK 0xB1 Previous Track key

210.0015555556

VK_MEDIA_STOP 0xB2 Stop Media key

VK_MEDIA_PLAY_PAUSE 0xB3 Play/Pause Media key

VK_LAUNCH_MAIL 0xB4 Start Mail key

VK_LAUNCH_MEDIA_SELECT 0xB5 Select Media key

VK_LAUNCH_APP1 0xB6 Start Application 1 key

VK_LAUNCH_APP2 0xB7 Start Application 2 key

- 0xB8-B9 Reserved

VK_OEM_1 0xBA Used for miscellaneous characters; it can vary by keyboard. For the US standard keyboard, the ';' key

VK_OEM_PLUS 0xBB For any country/region, the '+' key

VK_OEM_COMMA 0xBC For any country/region, the ',' key

VK_OEM_MINUS 0xBD For any country/region, the '-' key

VK_OEM_PERIOD 0xBE For any country/region, the '.' key

VK_OEM_2 0xBF Used for miscellaneous characters; it can vary by keyboard. For the US standard keyboard, the '/?' key

VK_OEM_3 0xC0 Used for miscellaneous characters; it can vary by keyboard. For the US standard keyboard, the '`~' key

- 0xC1-D7 Reserved

- 0xD8-DA Unassigned

210.0015555556

VK_OEM_4 0xDB Used for miscellaneous characters; it can vary by keyboard. For the US standard keyboard, the '[' key

VK_OEM_5 0xDC Used for miscellaneous characters; it can vary by keyboard. For the US standard keyboard, the '|' key

VK_OEM_6 0xDD Used for miscellaneous characters; it can vary by keyboard. For the US standard keyboard, the ']' key

VK_OEM_7 0xDE Used for miscellaneous characters; it can vary by keyboard. For the US standard keyboard, the 'single-quote/double-quote' key

VK_OEM_8 0xDF Used for miscellaneous characters; it can vary by keyboard.

- 0xE0 Reserved

0xE1 OEM specific

VK_OEM_102 0xE2 The keys on the US standard keyboard, or the \ key on the non-US 102-key keyboard

0xE3-E4 OEM specific

VK_PROCESSKEY 0xE5 IME PROCESS key

0xE6 OEM specific

VK_PACKET 0xE7 Used to pass Unicode characters as if they were keystrokes. The VK_PACKET key is the low word of a 32-bit Virtual Key value used for non-keyboard input methods. For more information, see Remark in KEYBDINPUT , SendInput , WM_KEYDOWN , and WM_KEYUP

- 0xE8 Unassigned

0xE9-F5 OEM specific

VK_ATTN 0xF6 Attn key

VK_CRSEL 0xF7 CrSel key

VK_EXSEL 0xF8 ExSel key

VK_EREOF 0xF9 Erase EOF key

VK_PLAY 0xFA Play key

VK_ZOOM 0xFB Zoom key

VK_NONAME 0xFC Reserved

VK_PA1 0xFD PA1 key

Reference

[Critical Qualitative Inquiry: Foundations and Futures](#)

[Handbook of Applied Behavior Analysis](#)